

Nutanix

NCP-5.10 Exam

Nutanix Certified Professional (NCP) 5.10 Exam

Thank you for Downloading NCP-5.10 exam PDF Demo

You can Buy Latest NCP-5.10 Full Version Download

https://www.certkillers.net/Exam/NCP-5.10

Version: 7.0

•				-
/ No.	-	-	-	• 7
Qu	-			
~~				

HOTSPOT

What is the proper sequence to perform a one-click upgrade to a Nutanix cluster? Item instructions: For each procedure, indicate the order in which that procedure must take place to meet the item requirements. Not all procedures are valid. Identify any invalid procedures using the drop-down option.

Answer Area

Step Select the Gear icon at top right of the page Step 1 Step 2 Step 3 Step 4 Step 5 Step 6 Invalid Step Select the component to upgrade Step 1 Step 2 Step 3 Step 4 Step 5 Step 6 Invalid Step Once the download completes, select Upgrade Step 1 Step 2 Step 3 Step 4 Step 5 Step 6 Invalid Step Log into Prism Central Step 1 Step 2 Step 3 Step 4 Step 5 Step 6 Invalid Step Select the User login name at the top right of the page Step 1 Step 2 Step 3 Step 4 Step 5 Step 6 Invalid Step On the left, select Upgrade Prism Central Step 1 Step 2 Step 3 Step 4 Step 5 Step 6 Invalid Step Click Download Step 1 Step 2 Step 3 Step 4 Step 5 Step 6 Invalid Step On the left under Settings, select Upgrade -Software Step 1 Step 2 Step 3 Step 4 Step 5 Step 6 Invalid Step Log in to Prism Element Step 1 Step 2 Step 3 Step 4 Step 5 Step 6 Invalid Step

_	Answer:
Step 1> Login into Prism Element.	
Step 2> Select the Gear Icon at top right of the page.	
Step 3> Click Upgrade Software.	
Step 4> Select the component to upgrade.	
Step 5> Click download.	
Step 6> Once the download completes, select upgrade.	
In valid:-	
1 - Select Prism Central.	
2 - Select user login.	
3 - On left select upgrade Prism Central.	
Question: 2	
Which command should an administrator run from the CLI to view the	uplink state of all AHV nodes
in the cluster?	
A allegh about malighe	
A. allssh show_uplinks B. manage_ovs show_uplinks	
C. allssh manage_ovs show_uplinks	
D. manage ovs show uplinks	
	Answer: C
Question: 3	
CPU utilization climbs above 90% on several VMs. This causes per	formance degradation for a
business-critical application.	

How can alerts be configured to notify the administrator before VM CPU utilization hits 90%?

- A. On a CVM, use ncli to set the VM CPU Check threshold for the critical VMs to a value below 90%.
- B. On the Health dashboard, locate the VM CPU Check and lower the alert threshold below 90%.
- C. On a CVM, configure a cron job to run the VM CPU Check more frequently and email the result.
- D. On the Alerts dashboard, ensure that the VM CPU usage alert is not set to auto-resolve.

Answer: B

Explanation:

https://portal.nutanix.com/page/documents/details?targetId=Web-Console-Guide-Prismv5 16:Web-Console-Guide-Prism-v5 16

Question:	4

When VM HA Reservation is enabled, what is the expected behavior for all failed VMs in the event of a host failure?

- A. Restart on a best-effort basis if resources are available
- B. Perform a live migration to other hosts in the AHV cluster
- C. Restart on other hosts in the AHV cluster
- D. Perform a live migration on a best-effort basis if resources are available

Answer: C

Question: 5

A customer wants to isolate a group of VMs within their Nutanix environment for security reasons. The customer creates a VM with two NICs to act as a firewall and installs the appropriate software and certificates.

However, no one from the outside can access the application.

What is the likely cause of this problem?

- A. A shared volume group must be used by all isolated VMs
- B. More than one NIC cannot be added to a VM
- C. One of the NICs needs to be configured on the internal VLAN
- D. Wireshark is installed on the NAT VM

Answer: C

Question: 6

What is the expected operation during node addition when the new node has a different AOS version?

- A. The entire cluster is upgraded to the latest one-click release.
- B. The node is added and a separate upgrade operation must be performed.
- C. The addition fails and forces the administrator to image using standalone Foundation.
- D. The node is automatically re-imaged using the software currently running in the cluster.

Answer: D

Explanation:

https://portal.nutanix.com/page/documents/details/?targetId=Web-Console-Guide-Prism-v511:wc-

Answer: A, D, E

<u>cluster-expand-wc-t</u>	
Question: 7	
Which component ensures uniform distribution of data throughout and speed up rebuilds?	ut the cluster to eliminate hot spots
A. CassandraB. Distributed Storage FabricC. Acropolis App Mobility FabricD. High Availability	
	Answer: A
Question: 8	
A VM in a 12-node Nutanix cluster is hosting an application requirements. Only three nodes in the cluster meet this requirement. The administrator wants to allow a general workload to be distributed and must make sure that the node hosting the VM meets its requirement how should the administrator perform this task? A. Create a sperate three-node cluster using the nodes that meet B. Configure VM-Host affinity for the nodes that meet the application VM with additional virtual GPUs.	ent. outed across all nodes in the cluster rements. the requirement. ion's GPU requirement.
D. Configure anti-affinity rules between the application VM arcluster.	id the other vivis running on the
	Answer: A
Question: 9	
Which three cluster operations require an administrator to reclain	n licenses?(Choose three)
A. Destroy a cluster.B. Upgrade a clusterC. Migrate a clusterD. Remove a Node from a clusterE. Move Nodes between clusters.	

Explanation:

https://portal.nutanix.com/page/documents/details/?targetId=Web Console Guide-

<u>Prism_v4_7:lic_licensing_managing_c</u> <u>Reclaiming Licenses (Including License Renewal)</u>

You can reclaim and optionally re-apply licenses for nodes in your clusters:

- You must reclaim licenses when you plan to destroy a cluster. First reclaim the licenses, then destroy the cluster. You do not need to reclaim Starter licenses. These licenses are automatically applied whenever you create a cluster, including after you have destroyed a cluster.
- Return licenses to your inventory when you remove one or more nodes from a cluster. Also, if you move nodes from one cluster to another, first reclaim the licenses, move the nodes, then re-apply the licenses.
- You can reclaim licenses for nodes in your clusters in cases where you want to make modifications or downgrade licenses. For example, applying an Ultimate license to all nodes in a cluster where some nodes are currently licensed as Pro and some nodes are licensed as Ultimate. You might also want to transition nodes from Ultimate to Pro licensing.
- You must reclaim licenses when you renew licenses. First reclaim the expired licenses, then apply new licenses.

|--|

An administrator is configuring cross-hypervisor DR from an ESXi cluster to a new AHV cluster. When the administrator migrates a protection domain to the AHV cluster, the VMs fail to boot. What should the administrator do to correct this problem?

- A. Increase the snapshot frequency to more than 6 hours.
- B. Uninstall VMware Tools from the VMs.
- C. Install Nutanix Guest Tools in the protected VMs.
- D. Add all VMs into a single consistency group.

Thank You for trying NCP-5.10 PDF Demo

To Buy Latest NCP-5.10 Full Version Download visit link below

https://www.certkillers.net/Exam/NCP-5.10

Start Your NCP-5.10 Preparation

[Limited Time Offer] Use Coupon "CKNET" for Further discount on your purchase. Test your NCP-5.10 preparation with actual exam questions.