IBM

LOT-441

IBM Social Software and Unified Communications Fundamentals

QUESTION: 110
When users are in an IBM Sametime Web Conference how can they share content from IBM Lotus Quickr places into their meeting?

A. Use voice controls to request it.
B. Nothing, it is shared automatically.
C. Close the meeting, get the file, upload it, and restart the meeting.
D. Drag and drop the content from the Lotus Quickr place into the Web conference.

Answer: D

QUESTION: 111
Which node in the IBM Lotus Quickr server's qpconfig.xml file contains configuration settings for integrating Lotus Quickr with an IBM Enterprise Content Management server?

A. <integration>
B. <ecm_integration>
C. <content_manager_integration>
D. <enterprise_content_manager_integration>

Answer: B

QUESTION: 112
If the administrator needs to fix an IBM Lotus Quickr place, the QPTOOL server command can be used to lock it. What is the correct syntax to lock a place?

A. load qptoollock placename
B. load qptool placename lock
C. load qptool lock placename
D. load qptool lock -p placename

Answer: D

QUESTION: 113
What are the minimum and recommended amounts of memory (RAM) on an IBM Lotus Quickr server?

A. Minimum of 1 GB RAM, recommended 2 GB RAM
B. Minimum of 2 GB RAM, recommended 4 GB RAM
C. Minimum of 4 GB RAM, recommended 8 GB RAM
D. Minimum of 6 GB RAM, recommended 8 GB RAM

Answer: B

QUESTION: 114
Which command is used to restart IBM Lotus Quickr?

A. restart quickr
B. restart task http
C. load qptool restart
D. restart task quickr

Answer: B

QUESTION: 115
Which database holds place usage statistics in IBM Lotus Quickr 8.5.1?

A. names.nsf
B. placecatalog.nsf
C. placestatistics.nsf
D. quickrstatistics.nsf

Answer: C

QUESTION: 116
If the administrator wants the IBM Lotus Quickr Connectors to install without prompting the user at all, what should be included after qkrconn.exe /install?

A. /quiet
B. /silent
C. /noask
D. /noprompt

Answer: A

QUESTION: 117
How would an administrator rebuild the administration place (i.e. the /LotusQuickr/lotusquickr place) on an IBM Lotus Quickr server?

A. run the command load qptool rebuild -lotusquickr
B. run the command load qptool recreate -lotusquickr
C. bring down the server, delete the /LotusQuickr/lotusquickr place at the operating system level, and restart the server
D. log into Lotus Quickr using a browser, go to the Site Administration link, and click the Recreate Admin Place button

Answer: C

QUESTION: 118
What is the name of the group created in the IBM Lotus Domino Directory to specify who has super user access?

A. QpAdmins
B. QuickrAdmins
C. QPAdminsGroup
D. QuickPlaceAdministratorsSUGroup

Answer: D

QUESTION: 119
Which option is an officially supported IBM Lotus Quickr 8.5.1 environment?

A. IBM Lotus Domino 8.5 32-bit on a Microsoft Windows 2003 64-bit operating system
B. Lotus Domino 8.5.1 FP5 64-bit on a Windows 2008 64-bit operating system
C. Lotus Domino 8.5.1 FP5 32-bit on a Windows 2003 64-bit operating system
D. Lotus Domino 8.5.1 FP5 64-bit on a Windows 2003 64-bit operating system

Answer: C

QUESTION: 120
What is a current known limitation when integrating IBM Lotus Quickr 8.5.1 with IBM Lotus iNotes?

A. Users cannot view Lotus Quickr links in messages sent to them.
B. Users cannot save an attachment in mail they receive to a Lotus Quickr place.
C. Users cannot add a Lotus Quickr place from within their Lotus iNotes user preferences.
D. Lotus Quickr integration is not available for Lotus iNotes when users are offline or accessing a local archive database.

Answer: D

Download Full Version From https://www.certkillers.net

Pass your exam at First Attempt....Guaranteed!